

ITTEST

QUESTION & ANSWER

Guías de estudio precisos, Alta tasa de paso!



Ittest ofrece información actualizada de forma gratuita en un año!

Exam : **HP0-244**

Title : Advanced Backup

Troubleshooting & Tuning

Version: DEMO

1.HP Ultrium tape drives use the ATS (Adaptive Tape Speed) feature. The main purpose of ATS is to increase .

A.buffer capacity by varying the speed of the tape

B.tape write speed by adjusting the host transfer rate

C.overall performance by reducing the number of repositions

D.tape read speed by adjusting the host transfer rate

Correct:C

2. What is the maximum cable length of an LVD SCSI bus?

A.7 m

B.12 m

C.20.5 m

D.25 m

Correct:B

3. What happens if you connect an HVD (High Voltage Differential) HBA (host bus adapter) to an LVD (Low Voltage Differential) tape device?

A.The devices function correctly if you setup unique SCSI IDs and have proper termination.

B.The devices do not function together and you may damage them.

C.The devices function correctly after setting up the compatibility mode for the HBA.

D.The devices do not function together unless you use active termination.

Correct:B

4. What is an advantage of the Cartridge Memory (a memory chip located in the cartridge) of the LTO Ultrium technology (LTO-CM) over previous tape technologies?

A.It eliminates the need for barcodes and barcode readers in tape libraries.

B.Data such as tape identity, type, usage and tape contents is read from a chip rather than the system area on tape, which reduces the wear and tear of that particular section.

C.It contains troubleshooting information from the tape drive which can help to reduce overall repair times.

D.The Ultrium drive reads data for firmware upgrades from a chip rather than a tape which increases the speed of the upgrade procedure.

Correct:B

5. The DLT tape backward read compatibility of HP SuperDLT drives is possible due to the _____.

A.Magneto-Resistive Cluster (MRC) technology

B.additional magnetic read-head

C.Pivoting Optical Servo (POS) technology

D.low-dens mode switch

Correct:B

6.SCSI bus termination is ____.

A.optional

B.required and there must be one terminator for each device on the bus

C.required and there must be two terminators, one on each end of the bus

D.required and done automatically by all SCSI devices

Correct:C

7. Which tool, available at the HP web site, can size and configure the ideal backup solution for DAS, NAS and SAN environments using information you specify?

A.HP OpenView Data Protector configuration scripter

B.Backup Sizing Tool

C.Enterprise Backup Solution Configuration Matrix

D.HP StorageWorks Library and Tape Tools

Correct:B

8. Which HP StorageWorks tape drive is the most appropriate choice for enterprise businesses with 150 GB of data to backup?

A.DAT 24

B.DAT 72

C.DLT VS 80

D.Ultrium 460

Correct:D

9.Click the Exhibit button. A customer has one single ESL9326D/DX with 4 DLT8000 drives. Which tape drive is supported for the next drives being installed in this library?

Upgrade to drive	SOLT 220	SD(T 320	Ultrium 230	Ultrium 460	Media Partitioning	Media Partitioning	Media Partitioning
approach to anne	(Ukra 2 SCSI)	(Ultra 2 SCSI)	(Ultra 2 SCSI)	(Ultra 3 SCSI)			
library T	(Care 2 Seasy	Joint 1 Stay	(Sind 2 Staty	Jean o serry	DIT8000 & SOLT	SDCL & CTC	Ultrium 230 & 46
ESL9198DLX	Supported	Supported	Supported	Supported	Supported (IVD only)	Supported (EVD only)	Supported
requires	249632-821 ESI9000 SDVT Eri axia iži upgrade 234617-821 ESI 9000 Field Upgrade SDLT220 Add-Chi LVD Drive	249632-821 ESP000 SDLT Ent anii- klii upgrade 293414-821 ESI0001YD SDLTSTO drive upgrade 274673-821 ESP000 S MB Memory Madule	249632-821 ESI9000 SOLT Est airis iii upgrade 301930-821 ESI9000 I/O Ulblein 230 Upgrade Drive 274673-821 ESI9000 5 MB Menay Medule 302234-821 ESI9000 UNIVERSAL ICAD PORT	24903-2821 ESERODO SDLT Erit desis At upgrade 330934-821 ESERODO (TO Ubrism 460 Upgrade Drive 274673-821 ESERODO SMB Memory Madale 302254-821 ESERODO UNIVERSAL COMP FORT (configure simple drive per SCSI bus) a2400-160 arefoodeded NSE and M42402 externed NSE are Utter 3 CSSI			
ESL9198SL	Supported	Supported	Supported	Sapported	Supported (IVD only)	Supported (EVD anly)	Supported
requires	234617-821 ESI 9000 Field Upgrade SDLT220 Add Chi LVD Drive		991930-821 ESI9000 (70 Ulbiett 220 Ulgrande Drive 274673-821 ESI9000 S MB Minnay Micdule 302254-821 ESI9000 UNIVERSAL LOAD PORT	330834.821 EXPOOD CTO Ulbrism 400 Upgrade Drive 274073-821 EXPOOD S MB Memory Madala 802254-821 EXPOOD UNIVERSAL COAD PORT (configure single drive per SCST bus) 824001-F0 artibodded MSE and M24002 external NSE are Ulbra 3 SCSI			
ES19326D/DX	Supported (HVD only)	Supported (HVD only)	Mol supported	Not supported	Supported (HVD only)	Not supported	Not supported
requires	249632-821 ESI9000 SDLT Erf axis kit upgrade 234617-822 ESI 9000 SDLT220 Add-On HVD Drive	249632-821 ESI9000 SDLT Erf aviv kit apgrade 293415-821 ESI9000 HVD SDLT320 drive upgrade 274673-821 ESI9000 5 MB Memory Madule	х	х		x	х
ES19326S1	Supported	Supported	Supported	Supported	Supported (IVD only)	Supported (EVD only)	Supported
requires	234617-821 ESL 9000 SOLT220 LVD spyrode Drive	29414-621 ESIPODO IVD SCRISZO drive upgrade 274673-821 ESIPODO 5 MB Memory Madide	301930-821 ESISPODO IPO UNIVERSAL 230 Upgrado Drivo 274673-821 ESISPODO S ME Miemary Micaldo 302234-821 ESISPODO UNIVERSAL LOAD PORT	330834-B21 ESPODO LFO Ultriam 460 Upgrade Drive 274073-B21 ESPODO S MB Memory Madala 302254-B21 ESPODO UNIVERSAL LOAD PORF (cooligare single drive per SCST Eux) 424001-FO entewookded INSE and M2402 waternal INSE are Ultre 3 SCSI			

A.DLT 8000 drives only

B.SDLT220 or SDLT320

C.DLT8000, SDLT220 or SDLT320

D.SDLT220, SDLT320 or Ultrium230

Correct:C

10.Click the Exhibit button. A customer installed Virtual Replicator on a Windows 2000 host. Which backup applications are supported for backing up the Virtual Replicator disks? Select TWO.

ebruary 2004													
	HP Data Protector	Atempo Time Navigator	BakBono NotVault	CA BrightStor ARCserve	CA BrightStor EB	CommVault Galaxy	Legato NetWorker	Syncsort Backup Express	Tivoli Storage Manager	VERITAS Backup Exec	VERITAS NotBackup		
OpenView													
Storage Virtual Replicator									*		-		
OV-SAM				~		4	~	-	4		-		
Zero Downtime with XP	~												
Instant Recovery with XP	· ·												
StorageWorks													
Command View for ESL	~					4	~		4		-		
Continuous Access				~			~		~	~	NT/WIN2K onl		
Business Copy EVA	-	-				4			4	NT/WIN2K only	NT/WIN2K on		
Business Copy XP	·												
Tools and Utilities													
Smart Start	· ·	-	4	~	-	*	~	-	~	*	·		
Insight Manager				-	-	4	·	-	~	~			

A.HP Data Protector
B.Legato Networker
C.Tivoli Storage Manager
D.CommVault Galaxy
E.CA BrightStor EB

Correct:B C